



**Note:** This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.

2018/09/07 05:04 · prokushev · [0 Comments](#)

# Int 21H, AH=5DH, AL=0AH

## Version

3.1 and higher

## Brief

SET EXTENDED ERROR INFORMATION

## Family API

## Input

```
AX = 5D0Ah  
DS:DX -> 11-word DOS parameter list (see #01686)
```

## Return

nothing. next call to AH=59h will return values from fields AX,BX,CX,DX,DI, and ES in corresponding registers

## Macro

## Notes

documented for DOS 5+, but undocumented in earlier versions

the MS-DOS Programmer's Reference incorrectly states that this call was introduced in DOS 4, and fails to mention that the ERROR structure passed to this function is a DOS parameter list.

BUGS:DR DOS 3.41 and 5.0 read the value for ES from the DS field of the DPL; fortunately, MS-DOS ignores the DS field, allowing a generic routine which sets both DS and ES fields to the same value

Novell DOS 7 (through at least Update 4) does not save the pointer, which is always reported as 0000h:0000h by AH=59h; Update 15 fully supports this function

## See also

AH=59h/BX=0000h

## Note

Text based on [Ralf Brown Interrupt List Release 61](#)

<b>DOS API</b>	
Process manager	INT 20H, <b>INT 21H</b> : 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H, INT 27H, INT 28H
File manager	INT 25H, INT 26H, <b>INT 21H</b> : 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH
Character Device I/O	INT 29H, <b>INT 21H</b> : 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH
Signals	INT 23H, INT 24H, <b>INT 21H</b> : 3300H, 3301H, 3302H
Memory manager	<b>INT 21H</b> : 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H
Date and Time	<b>INT 21H</b> : 2AH, 2BH, 2CH, 2DH
Misc	<b>INT 21H</b> : 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H
NLS	<b>INT 21H</b> : 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H
Devices	<b>INT 21H</b> : 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H
Network	<b>INT 21H</b> : 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H
<b>osFree Macro Library</b>	
Video I/O	<a href="#">@SetMode</a> <a href="#">@SetCurSz</a> <a href="#">@SetCurPos</a> <a href="#">@GetCur</a> <a href="#">@SetPage</a> <a href="#">@ScrollUp</a> <a href="#">@ScrollDn</a> <a href="#">@Scroll</a> <a href="#">@GetChAtr</a> <a href="#">@PutChAtr</a> <a href="#">@PutCh</a> <a href="#">@SetPalet</a> <a href="#">@SetColor</a> <a href="#">@SetDot</a> <a href="#">@GetDot</a> <a href="#">@WrtTTY</a> <a href="#">@VideoState</a> <a href="#">@GetMode</a> <a href="#">@GetDisplay</a> <a href="#">@GetVideoState</a> <a href="#">@GetEGInfo</a> <a href="#">@Cls</a>
Hardware info	<a href="#">@Equipment</a> <a href="#">@MemSize</a>
Serial I/O	<a href="#">@AuxInit</a> <a href="#">@AuxSendChar</a> <a href="#">@AuxRecieveChar</a> <a href="#">@AuxStatus</a>
Tape I/O	<a href="#">@TapeOn</a> <a href="#">@TapeOff</a> <a href="#">@TapeRead</a> <a href="#">@TapeWrite</a>
Keyboard I/O	<a href="#">@KbdStatus</a> <a href="#">@CharIn</a> <a href="#">@CharPeek</a>
Printer I/O	<a href="#">@PrnPrint</a> <a href="#">@PrnInit</a> <a href="#">@PrnStatus</a>
Disk I/O	<a href="#">@DskReset</a> <a href="#">@DskStatus</a> <a href="#">@DskRead</a> <a href="#">@DskWrite</a> <a href="#">@DskVerify</a> <a href="#">@DskFormat</a>

<b>osFree Macro Library</b>	
Date and Time	@SetTime @GetTime
Mouse	@MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion
Memory manager	@ModBlok SET_BLOCK

2022/10/04 14:28 · prokushev · 0 Comments

2018/09/04 17:23 · prokushev · 0 Comments

<b>Family API</b>		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From: <https://osfree.su/doku/> - **osFree wiki**

Permanent link: <https://osfree.su/doku/doku.php?id=en:docs:dos:api:int21:5d:0a>

Last update: **2024/05/03 07:24**

