2025/03/13 15:07 1/3 Int 31H, AH=03H, AL=02H



Note: This API calls are shared between DOS and Win16 personality.

DPMI is a shared interface for DOS applications to access Intel 80286+ CPUs services. DOS DMPI host provides core services for protected mode applications. Multitasking OS with DOS support also provides DMPI in most cases. Windows standard and extended mode kernel is a DPMI client app. Standard and extended mode kernel differs minimally and shares common codebase. Standard Windows kernel works under DOSX extender. DOSX is a specialized version of 16-bit DPMI Extender (but it is standard DPMI host). Standard mode is just DPMI client, exnhanced mode is DPMI client running under Virtual Machime Manager (really, multitasker which allow to run many DOS sessions). Both modes shares DPMI interface for kernel communication. The OS/2 virtual DOS Protected Mode Interface (VDPMI) device driver provides Version 0.9 DPMI support for virtual DOS machines. Win16 (up to Windows ME) provides Version 0.9 DPMI support. Windows in Standard Mode provides DPMI services only for Windows Applications, not DOS sessions.

DPMI host often merged with DPMI extender. Usually DPMI extender provide DPMI host standard services and DOS translation or True DPMI services.

2021/08/05 10:15 · prokushev · 0 Comments

Int 31H, AH=03H, AL=02H

Version

0.9

Brief

Call Real Mode Procedure With IRET Frame

Input

AX = 0302HBH = flags

Bit Significance

0 reserved for historical reason, must be zero

1-7 reserved, must be zero

CX = number of words to copy from protected mode to real mode stack ES:(E)DI = selector:offset of real mode register data structure in the following format:

Offset	Length	Contents
00H	4	DI or EDI
04H	4	SI or ESI
08H	4	BP or EBP
0CH	4	reserved, ignored
10H	4	BX or EBX
14H	4	DX or EDX
18H	4	CX or ECX
1CH	4	AX or EAX
20H	2	CPU status flags
22H	2	ES
24H	2	DS
26H	2	FS
28H	2	GS
2AH	2	IP
2CH	2	CS
2EH	2	SP
30H	2	SS

```
if function successful
Carry flag = clear
ES:(E)DI = selector:offset of modified real mode register data structure

if function unsuccessful
Carry flag = set
AX = error code
8012H  linear memory unavailable (stack)
8013H  physical memory unavailable (stack)
8014H  backing store unavailable (stack)
8021H  invalid value (CX too large)
```

Notes

Simulates a FAR CALL with flags pushed on the stack to a real mode procedure. The real mode routine must return by executing an IRET instruction.

32-bit programs must use ES:EDI to point to the real mode register data structure. 16-bit programs should use ES:DI.

The CS:IP in the real mode register data structure specifies the address of the real mode procedure to call.

If the SS:SP fields in the real mode register data structure are zero, a real mode stack will be provided by the DPMI host. Otherwise, the real mode SS:SP will be set to the specified values before the interrupt handler is called.

The flags specified in the real mode register data structure will be pushed on the real mode stack's IRET frame. The procedure will be called with the interrupt and trace flags clear.

2025/03/13 15:07 3/3 Int 31H, AH=03H, AL=02H

Values placed in the segment register positions of the data structure must be valid for real mode; i.e. the values must be paragraph addresses and not selectors.

All general register fields in the data structure are DWORDs so that 32-bit registers can be passed to real mode. Note, however, that 16-bit hosts are not required to pass the high word of 32-bit general registers or the FS and GS segment registers to real mode even when running on an 80386 or later CPU.

The target real mode handler or procedure must return with the stack in the same state as when it was called. This means that the real mode code may switch stacks while it is running, but must return on the same stack that it was called on and must return with an IRET or discard the flags from the stack with a RETF(2).

When this function returns, the real mode register data structure will contain the values that were returned by the real mode procedure.

It is the caller's responsibility to remove any parameters that were pushed on the protected mode stack.

See also

Note

Text based on http://www.delorie.com/djgpp/doc/dpmi/

DPMI			
Process manager	INT 2FH 1680H, 1687H		
Signals			
Memory manager			
Misc	INT 2FH 1686H, 168AH		
Devices			

2021/08/13 14:23 · prokushev · 0 Comments

From:

https://www.osfree.org/doku/ - osFree wiki

Permanent link:

https://www.osfree.org/doku/doku.php?id=en:docs:dpmi:api:int31:03:02

Last update: 2021/08/27 03:05

