



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

**Note:** This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

This call scrolls the entire display buffer (or area specified within the display buffer) to the left.

### Syntax

VioScrollLf (TopRow, LeftCol, BotRow, RightCol, Lines, Cell, VioHandle)

### Parameters

;TopRow (USHORT) - input : Top row to be scrolled. ;LeftCol (USHORT) - input : Left column to be scrolled. ;BotRow (USHORT) - input : Bottom row to be scrolled. ;RightCol (USHORT) - input : Right column to be scrolled. ;Lines (USHORT) - input : Number of columns to be inserted at the right of the screen area being scrolled. If 0 is specified, no lines are scrolled. ;Cell (PBYTE) - input : Address of the character attribute(s) pair (2 or 4 bytes) used as a fill character on inserted columns. ;VioHandle (HVIO) - input : This must be zero unless the caller is a Presentation Manager application, in which case it must be the value returned by VioGetPs.

### Return Code

rc (USHORT) - return Return code descriptions are: \* 0 NO\_ERROR \* 355 ERROR\_VIO\_MODE \* 358 ERROR\_VIO\_ROW \* 359 ERROR\_VIO\_COL \* 436 ERROR\_VIO\_INVALID\_HANDLE \* 465 ERROR\_VIO\_DETACHED

### Remarks

TopRow = 0 and LeftCol = 0 identifies the top left corner of the screen.

If a value greater than the maximum value is specified for TopRow, LeftCol, BotRow, RightCol, or Lines, the maximum value for that parameter is used.

If TopRow and LeftCol = 0 and if BotRow, RightCol, and Lines = 65535 (or -1 in assembler language), the entire screen is filled with the character-attribute pair defined by Cell.

### Example Code

## C Binding

```
<PRE> #define INCL_VIO
```

```
USHORT rc = VioScrollLf(TopRow, LeftCol, BotRow, RightCol, Lines, Cell,
```

```
VioHandle);
```

```
USHORT TopRow; /* Top row */ USHORT LeftCol; /* Left column */ USHORT BotRow; /* Bottom row */
USHORT RightCol; /* Right column */ USHORT Lines; /* Number of lines */ PBYTE Cell; /* Cell to be
written */ HVIO VioHandle; /* Video Handle */
```

```
USHORT rc; /* return code */ </PRE>
```

## MASM Binding

```
<PRE> EXTRN VioScrollLf:FAR INCL_VIO EQU 1
```

```
PUSH WORD TopRow ;Top row PUSH WORD LeftCol ;Left column PUSH WORD BotRow ;Bottom row
PUSH WORD RightCol ;Right column PUSH WORD Lines ;Number of lines PUSH@ OTHER Cell ;Cell to
be written PUSH WORD VioHandle ;Video Handle CALL VioScrollLf
```

```
Returns WORD </PRE>
```

# Note

Text based on <http://www.edm2.com/index.php/VioScrollLf>

Family API		
DOS	Process Manager	<a href="#">DosBeep</a> <a href="#">DosExit</a> <a href="#">DosSleep</a> <a href="#">DosExecPgm</a>
	File Manager	<a href="#">DosChDir</a> <a href="#">DosChgFilePtr</a> <a href="#">DosClose</a> <a href="#">DosDelete</a> <a href="#">DosDupHandle</a> <a href="#">DosMkDir</a> <a href="#">DosMove</a> <a href="#">DosQCurDir</a> <a href="#">DosQCurDisk</a> <a href="#">DosSetFileMode</a> <a href="#">DosOpen</a> <a href="#">DosQFileInfo</a> <a href="#">DosRead</a> <a href="#">DosQFileMode</a> <a href="#">DosQFSInfo</a> <a href="#">DosQVerify</a> <a href="#">DosRmDir</a> <a href="#">DosSelectDisk</a> <a href="#">DosFindClose</a> <a href="#">DosFindFirst</a> <a href="#">DosFindNext</a> <a href="#">DosSetFileInfo</a> <a href="#">DosSetVerify</a> <a href="#">DosWrite</a> <a href="#">DosFileLocks</a> <a href="#">DosSetFHandState</a> <a href="#">DosNewSize</a> <a href="#">DosBufReset</a> <a href="#">DosQFHandState</a> <a href="#">DosSetFSinfo</a> <a href="#">DosShutdown</a>
	Memory Manager	<a href="#">DosFreeSeg</a> <a href="#">DosSubAlloc</a> <a href="#">DosSubFree</a> <a href="#">DosSubSet</a> <a href="#">DosAllocHuge</a> <a href="#">DosAllocSeg</a> <a href="#">DosReallocHuge</a> <a href="#">DosReallocSeg</a> <a href="#">DosGetHugeShift</a> <a href="#">DosCreateCSAlias</a>
	NLS	<a href="#">DosCaseMap</a> <a href="#">DosGetCtryInfo</a> <a href="#">DosGetDBCSEv</a> <a href="#">DosSetCtryCode</a> <a href="#">DosGetCollate</a> <a href="#">DosGetMessage</a> <a href="#">DosInsMessage</a> <a href="#">DosPutMessage</a>
	Date and Time	<a href="#">DosSetDateTime</a> <a href="#">DosGetDateTime</a>
	Devices	<a href="#">DosDevConfig</a> <a href="#">DosDevIOCtl</a> <a href="#">DosDevIOCtl2</a>
	Signals	<a href="#">DosHoldSignal</a> <a href="#">DosSetSigHandler</a>
	Misc	<a href="#">BadDynLink</a> <a href="#">DosGetEnv</a> <a href="#">DosGetMachineMode</a> <a href="#">DosGetVersion</a> <a href="#">DosError</a> <a href="#">DosErrClass</a> <a href="#">DosSetVec</a>

<b>Family API</b>	
KBD	<a href="#">KbdCharIn</a> <a href="#">KbdFlushBuffer</a> <a href="#">KbdGetStatus</a> <a href="#">KbdSetStatus</a> <a href="#">KbdStringIn</a> <a href="#">KbdPeek</a>
VIO	<a href="#">VioGetBuf</a> <a href="#">VioGetConfig</a> <a href="#">VioGetCurPos</a> <a href="#">VioGetCurType</a> <a href="#">VioGetPhysBuf</a> <a href="#">VioReadCellStr</a> <a href="#">VioReadCharStr</a> <a href="#">VioScrollUp</a> <a href="#">VioScrollDn</a> <a href="#">VioScrollLf</a> <a href="#">VioScrollRt</a> <a href="#">VioScrUnLock</a> <a href="#">VioSetCurPos</a> <a href="#">VioSetCurType</a> <a href="#">VioSetMode</a> <a href="#">VioGetMode</a> <a href="#">VioShowBuf</a> <a href="#">VioWrtCellStr</a> <a href="#">VioWrtCharStr</a> <a href="#">VioWrtCharStrAtt</a> <a href="#">VioWrtNAttr</a> <a href="#">VioWrtNCell</a> <a href="#">VioWrtNChar</a> <a href="#">VioWrtTTY</a> <a href="#">VioScrLock</a> <a href="#">VioPopUp</a>
Tools	<a href="#">BIND</a>
Modules	<a href="#">DOSCALLS.DLL</a> <a href="#">VIOCALLS.DLL</a> <a href="#">KBDCALLS.DLL</a> <a href="#">MSG.DLL</a>
Libraries	<a href="#">API.LIB</a> <a href="#">OS2386.LIB</a> <a href="#">FAPI.LIB</a> <a href="#">DOSCALLS.LIB</a> <a href="#">SUBCALLS.LIB</a>

2018/08/25 15:05 · [prokushev](#) · [0 Comments](#)

From:  
<https://osfree.su/doku/> - **osFree wiki**

Permanent link:  
<https://osfree.su/doku/doku.php?id=en:docs:fapi:vioscrolllf&rev=1629447034>

Last update: **2021/08/20 08:10**

