



Note: This API calls are shared between DOS and Win16 personality.

DPMI is a shared interface for DOS applications to access Intel 80286+ CPUs services. DOS DMPI host provides core services for protected mode applications. Multitasking OS with DOS support also provides DPMI in most cases. Windows standard and extended mode kernel is a DPMI client app. Standard and extended mode kernel differs minimally and shares common codebase. Standard Windows kernel works under DOSX extender. DOSX is a specialized version of 16-bit DPMI Extender (but it is standard DPMI host). Standard mode is just DPMI client, enhanced mode is DPMI client running under Virtual Machine Manager (really, multitasker which allow to run many DOS sessions). Both modes shares DPMI interface for kernel communication. The OS/2 virtual DOS Protected Mode Interface (VDPMI) device driver provides Version 0.9 DPMI support for virtual DOS machines. Win16 (up to Windows ME) provides Version 0.9 DPMI support. Windows in Standard Mode provides DPMI services only for Windows Applications, not DOS sessions.

DPMI host often merged with DPMI extender. Usually DPMI extender provide DPMI host standard services and DOS translation or True DPMI services.

2021/08/05 10:15 · prokushev · [0 Comments](#)

Int 31H, AH=02H, AL=12H

Version

1.0

Brief

Set Extended Processor Exception Handler Vector (Protected Mode)

Input

```
AX = 0212H
BL = exception/fault number (00H-1FH)
CX:(E)DX = selector:offset of exception handler
```

Return

```
if function successful
Carry flag = clear
```

```
if function unsuccessful
Carry flag = set
AX = error code
8021H   invalid value (BL not in range 00H-1FH)
8022H   invalid selector
```

Notes

DPMI 1.0 clients should use this function in preference to Int 31H Function 0203H.

The protected mode exceptions are sent to the protected mode handler of the current client.

Refer to the rules for descriptor usage in Appendix D.

See also

Note

Text based on <http://www.delorie.com/djgpp/doc/dpmi/>

DPMI	
Process manager	INT 2FH 1680H, 1687H
Signals	
Memory manager	
Misc	INT 2FH 1686H, 168AH
Devices	

2021/08/13 14:23 · prokushev · [0 Comments](#)

From:

<http://www.osfree.ru/doku/> - **osFree wiki**

Permanent link:

<http://www.osfree.ru/doku/doku.php?id=en:docs:dpmi:api:int31:02:12>

Last update: **2021/08/27 02:48**

