



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

VioSetMode

This call sets the mode of the display.

Syntax

VioSetMode (ModeData, VioHandle)

Parameters

;ModeData ([PVIOMODEINFO](#)) - input : Address of the mode characteristics structure: ::length (USHORT) : Input parameter to VioSetMode. Length specifies the length of the data structure in bytes including Length itself. The minimum structure size required is 3 bytes. OS/2 sets to the first mode (in the list of modes supported by this display configuration) with a data structure matching the mode data specified. ::type (UCHAR): Mode characteristics bit mask: 'Bit Description' 7-4 Reserved, set to zero. 3 0 = VGA-compatible modes 0 thru 13H.

1 = Native mode.

2 0 = Enable color burst

1 = Disable color burst.

1 0 = Text mode.

1 = Graphics mode.

0 0 = Monochrome compatible mode.

1 = Other.

::numcolors (UCHAR): Number of colors defined as a power of 2. This is equivalent to the number of color bits that define the color, for example: 'Value Definition' 0 Monochrome modes 7, 7+, and F. 1 2 colors. 2 4 colors. 4 16 colors. 8 256 colors. ::textcols (USHORT): Number of text columns. ::textrows (USHORT): Number of text rows. ::pelcols (USHORT): Horizontal resolution, number of pel columns. ::pelrows (USHORT): Vertical resolution, number of pel rows. ::Attribute Format (UCHAR):

Identifies the format of the attributes. ::Number of Attributes (UCHAR): Identifies the number of attributes in a character cell. ::Buffer Address (ULONG): 32-bit physical address of the physical display buffer for this mode. ::Buffer Length (ULONG): Length of the physical display buffer for this mode. ::Full Buffer Size (ULONG): Size of the buffer required for a full save of the physical display buffer for this mode. ::Partial Buffer Size (ULONG): Size of the buffer required for a partial (pop-up) save of the physical display buffer for this mode. ::Extended Data Area Address (PCH): Far address to an extended mode data structure or zero if none. The format of the extended mode data structure is determined by the device driver and is unknown to OS/2. ;VioHandle (HVIO) - input : Reserved word of 0s.

Return Code

rc (USHORT) - return Return code descriptions are: *0 NO_ERROR *355 ERROR_VIO_MODE *430 ERROR_VIO_ILLEGAL_DURING_POPUP *436 ERROR_VIO_INVALID_HANDLE *438 ERROR_VIO_INVALID_LENGTH *465 ERROR_VIO_DETACHED *467 ERROR_VIO_FONT *468 ERROR_VIO_USER_FONT *494 ERROR_VIO_EXTENDED_SG

Remarks

VioSetMode initializes the cursor position and type.

VioSetMode does not clear the screen. To clear the screen, use one of the VioScrollxx calls.

The disable color burst bit in the Type field in the VioSetMode data structure is functional only for the CGA and VGA. This bit causes the color portion of the video signal to be suppressed, producing a black and white mode on composite monitors attached to the CGA. On VGA, the bit causes the color lookup table to be loaded with values that produce shades of gray instead of colors, again producing a black and white mode. For all other combinations of adapters and displays, the setting of this bit is recorded and returned on any subsequent VioGetMode call, but otherwise is ignored.

For text modes in full-screen sessions, the number of rows on the screen is determined by the availability of fonts of the correct size. For any specified mode, the size of the character defined by the font must be (Horizontal Resolution)/(Text Columns) dots wide and (Vertical Resolution)/(Text Rows) dots high. For example, an 8x8 font would support 39 through 43 text rows if the screen resolution were 640x350.

If VioSetState request type 6 has been issued previously to select the target display configuration for VioSetMode, the mode is set on the display configuration selected. If that display configuration does not support the mode specified, an error is returned.

Assuming no target display configuration for VioSetMode is selected, the mode is set on the primary configuration. If the primary configuration does not support the mode specified, the mode is set on the secondary configuration.

The table below shows the VioSetMode parameters required to set all the modes supported by the CGA, EGA, VGA, and PS/2 Display Adapters. The modes native to the 8514/A and other advanced video adapters are set with the Adapter (programming) Interface to these adapters, not VioSetMode.

Note: Although graphics mode support is provided in VioSetMode, this support is not provided by the

Base Video Handlers provided with OS/2.

Table 5-1. Display Mode Attributes Supported by Adapters

| BIOS MODE | TYPE | COLOR | COLS | ROWS | HRES | VRES | VALID ADAPTER/DISPLAY COMBINATIONS [EMULATED] |
|------------------|-------------|--------------|-------------|-------------|-------------|-------------|--|
| 0 | 5 | 4 | 40 | 25 | 320 | 200 | [CGA/CD], CGA/Comp, [EGA/CD], [EGA/ECD], VGA/Mono, VGA/Color, VGA/Plasma |
| 0* | 5 | 4 | 40 | 25 | 320 | 350 | [EGA/ECD], VGA/Mono, VGA/Color, VGA/Plasma |
| 0+ | 5 | 4 | 40 | 25 | 360 | 400 | VGA/Mono, VGA/Color |
| 0# | 5 | 4 | 40 | 25 | 320 | 400 | VGA/Mono, VGA/Color, VGA/Plasma |
| 1 | 1 | 4 | 40 | 25 | 320 | 200 | CGA/CD, CGA/Comp, EGA/CD, EGA/ECD, [VGA/Mono], VGA/Color, [VGA/Plasma] |
| 1* | 1 | 4 | 40 | 25 | 320 | 350 | EGA/ECD, [VGA/Mono], VGA/Color, [VGA/Plasma] |
| 1+ | 1 | 4 | 40 | 25 | 360 | 400 | [VGA/Mono], VGA/Color |
| 1# | 1 | 4 | 40 | 25 | 320 | 400 | [VGA/Mono], VGA/Color, [VGA/Plasma] |
| 2 | 5 | 4 | 80 | 25 | 640 | 200 | [CGA/CD], CGA/Comp, [EGA/CD], [EGA/ECD], VGA/Mono, VGA/Color, VGA/Plasma |
| 2* | 5 | 4 | 80 | 25 | 640 | 350 | [EGA/ECD], VGA/Mono, VGA/Color, VGA/Plasma |
| 2+ | 5 | 4 | 80 | 25 | 720 | 400 | VGA/Mono, VGA/Color |
| 2# | 5 | 4 | 80 | 25 | 640 | 400 | VGA/Mono, VGA/Color, VGA/Plasma |
| 3 | 1 | 4 | 80 | 25 | 640 | 200 | CGA/CD, CGA/Comp, EGA/CD, EGA/ECD, [VGA/Mono], VGA/Color, [VGA/Plasma] |
| 3* | 1 | 4 | 80 | 25 | 640 | 350 | EGA/ECD, [VGA/Mono], VGA/Color, [VGA/Plasma] |
| 3+ | 1 | 4 | 80 | 25 | 720 | 400 | [VGA/Mono], VGA/Color |
| 3# | 1 | 4 | 80 | 25 | 640 | 400 | [VGA/Mono], VGA/Color, [VGA/Plasma] |
| 7 | 0 | 0 | 80 | 25 | 720 | 350 | MPA/MD, EGA/MD, VGA/Mono, VGA/Color |
| 7+ | 0 | 0 | 80 | 25 | 720 | 400 | VGA/Mono, VGA/Color |
| 7# | 0 | 0 | 80 | 25 | 640 | 400 | VGA/Mono, VGA/Color, VGA/Plasma |
| n/a | 0 | 0 | 80 | 25 | 640 | 350 | VGA/Mono, VGA/Color, VGA/Plasma |
| n/a | 1 | 4 | 80 | 30 | 720 | 480 | [VGA/Mono], VGA/Color |
| n/a | 1 | 4 | 80 | 30 | 640 | 480 | [VGA/Mono], VGA/Color, [VGA/Plasma] |
| 4 | 3 | 2 | [40] | [25] | 320 | 200 | CGA/CD, CGA/Comp, EGA/CD, EGA/ECD, [VGA/Mono], VGA/Color, [VGA/Plasma] |
| 5 | 7 | 2 | [40] | [25] | 320 | 200 | [CGA/CD], CGA/Comp, [EGA/CD], [EGA/ECD], VGA/Mono, VGA/Color, VGA/Plasma |
| 6 | 3 | 1 | [80] | [25] | 640 | 200 | CGA/CD, CGA/Comp, EGA/CD, EGA/ECD, VGA/Mono, VGA/Color, VGA/Plasma |
| D | 3 | 4 | [40] | [25] | 320 | 200 | EGA/CD, EGA/ECD, [VGA/Mono], VGA/Color, [VGA/Plasma] |
| E | 3 | 4 | [80] | [25] | 640 | 200 | EGA/CD, EGA/ECD, [VGA/Mono], VGA/Color, [VGA/Plasma] |
| F | 2 | 0 | [80] | [25] | 640 | 350 | EGA/MD, VGA/Mono, VGA/Color, VGA/Plasma |
| 10 | 3 | 4 | [80] | [25] | 640 | 350 | EGA/ECD, [VGA/Mono], VGA/Color, [VGA/Plasma] |
| 11 | 3 | 1 | [80] | [30] | 640 | 480 | VGA/Mono, VGA/Color, VGA/Plasma |
| 12 | 3 | 4 | [80] | [30] | 640 | 480 | [VGA/Mono], VGA/Color, [VGA/Plasma] |
| 13 | 3 | 8 | [40] | [25] | 320 | 200 | [VGA/Mono], VGA/Color, [VGA/Plasma] |
| n/a | 11 | 8 | [80] | [30] | 640 | 480 | [8514A/Mono], 8514A/Color |

| BIOS MODE | TYPE | COLOR | COLS | ROWS | HRES | VRES | VALID ADAPTER/DISPLAY COMBINATIONS [EMULATED] |
|-----------|------|-------|------|------|------|------|---|
| n/a | 11 | 4 | [80] | [30] | 640 | 480 | [8514A/Mono], 8514A/Color |
| n/a | 11 | 8 | [85] | [38] | 1024 | 768 | [8514A/HMono], 8514A/HColor |
| n/a | 11 | 4 | [85] | [38] | 1024 | 768 | [8514A/HMono], 8514A/HColor |

MPA Monochrome/Printer Adapter
 CGA Color Graphics Adapter
 EGA Enhanced Graphics Adapter
 VGA Video Graphics Array, PS/2 Display Adapter
 8514A 8514/A Display Adapter

MD 5151 Monochrome Display
 CD 5153 Color Display
 ECD 5154 Enhanced Color Display
 MONO 8503 PS/2 Monochrome Display, 8507/8604 Display
 HMONO 8507/8604 Display
 COLOR 8512/13 PS/2 Color Display, 8514 Display
 HCOLOR 8514 Display
 PLASMA Plasma Display Panel
 COMP Composite Video Monitor

Notes: #Types 0, 1, and 5 are text modes; types 2, 3, 7, and 11 are graphics modes. #For BIOS modes 0, 2, 5, the color burst is disabled on the CGA and VGA. #The Personal System/2 Display Adapter 8514/A™ has advanced function modes, which are supported through the 8514/A display adapter interface, not the VIO Subsystem. Refer to the Personal System/2 Display Adapter 8514/A Technical Reference for details of this support.

Note: For text modes in full-screen, the number of rows may differ from the mode table due to the availability of fonts of the correct size as described above.

PM Considerations

Windowable VIO sessions support only 80-column, color text modes. When VioSetMode is called from a Windowable VIO session, it only verifies that an 80-column text mode was requested, with Text Rows between 1 and 255. The resulting mode, which can be queried using VioGetMode, always has Type = 1, Color = 4, Text Columns = 80, Text Rows = requested Text Rows, Horizontal Resolution = 640, and Vertical Resolution = 16 * (Text Rows).

Family API Considerations

Some options operate differently in the DOS mode than in the OS/2 mode. Therefore, the following consideration applies to VioSetMode when coding for the DOS mode:

VioSetMode clears the screen.

Bindings

C Binding

```
<PRE> typedef struct _VIOMODEINFO {
```

```

USHORT cb;                /* Length of the entire data structure */
UCHAR fbType;            /* Bit mask of mode being set */
UCHAR color;            /* Number of colors (power of 2) */
USHORT col;             /* Number of text columns */
USHORT row;            /* Number of text rows */
USHORT hres;           /* Horizontal resolution */
USHORT vres;           /* Vertical resolution */
UCHAR fmt_ID;          /* Attribute format */
UCHAR attrib;         /* Number of attributes */
ULONG buf_addr;
ULONG buf_length;
ULONG full_length;
ULONG partial_length;
PCH ext_data_addr;
} VIOMODEINFO;
```

```
typedef VIOMODEINFO far *PVIOMODEINFO;
```

```
#define INCL_VIO
```

```
USHORT rc = VioSetMode(ModeData, VioHandle);
```

```
PVIOMODEINFO ModeData; /* Mode characteristics */ HVIO VioHandle; /* Video handle */
```

```
USHORT rc; /* return code */ </PRE>
```

MASM Binding

```

VIOMODEINFO struc
    viomi_cb          dw ? ;Length of the entire data structure
    viomi_fbType      db ? ;Bit mask of mode being set
    viomi_color       db ? ;Number of colors (power of 2)
    viomi_col         dw ? ;Number of text columns
    viomi_row         dw ? ;Number of text rows
    viomi_hres        dw ? ;Horizontal resolution
    viomi_vres        dw ? ;Vertical resolution
    viomi_fmt_ID      db ? ;Attribute format
    viomi_attrib      db ? ;Number of attributes
    viomi_buf_addr    dd ? ;
    viomi_buf_length  dd ? ;
    viomi_full_length dd ? ;
    viomi_partial_length dd ? ;
    viomi_ext_data_addr dd ? ;
```

```

VIOMODEINFO ends

EXTRN  VioSetMode:FAR
INCL_VIO      EQU 1

PUSH@  OTHER    ModeData      ;Mode characteristics
PUSH   WORD     VioHandle     ;Video handle
CALL   VioSetMode

Returns  WORD
    
```

Note

Text based on [http://www.edm2.com/index.php/VioSetMode_\(FAPi\)](http://www.edm2.com/index.php/VioSetMode_(FAPi))

| Family API | | |
|------------|---|--|
| DOS | Process Manager | DosBeep DosExit DosSleep DosExecPgm |
| | File Manager | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSInfo DosShutdown |
| | Memory Manager | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias |
| | NLS | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage |
| | Date and Time | DosSetDateTime DosGetDateTime |
| | Devices | DosDevConfig DosDevIOCtl DosDevIOCtl2 |
| | Signals | DosHoldSignal DosSetSigHandler |
| | Misc | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec |
| KBD | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek | |
| VIO | VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp | |
| Tools | BIND | |
| Modules | DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL | |
| Libraries | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB | |

2018/08/25 15:05 · prokushev · 0 Comments

From:
<https://osfree.su/doku/> - **osFree wiki**

Permanent link:
<https://osfree.su/doku/doku.php?id=en:docs:fapi:viosetmode&rev=1630067815>

Last update: **2021/08/27 12:36**

