



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

DosPutMessage

This call outputs the message in a buffer passed by a caller to the specified handle. The function formats the buffer to prevent words from wrapping if displayed to a screen.

Syntax

DosPutMessage (FileHandle, MessageLength, MessageBuffer)

Parameters

;FileHandle (USHORT) - input : Handle of the output file or device. ;MessageLength (USHORT) - input : Length of the message to be output. ;MessageBuffer (PCHAR) - input : Address of the buffer that contains the returned message.

Return Code

rc (USHORT) - return Return code descriptions are: * 0 NO_ERROR * 6 ERROR_INVALID_HANDLE * 19 ERROR_WRITE_PROTECT * 321 ERROR_MR_UN_PERFORM

Remarks

Screen width is assumed to be 80 characters. The DosPutMessage call counts a CR/LF in the 80 characters that it tries to write to the screen. If a word extends past column 78, it is put on the next line. DosPutMessage assumes the starting cursor position is column one when handling a word wrap.

If the last character to be positioned on a line is a double-byte character that would be bisected, the rule above ensures that the character is not bisected.

Example Code

C Binding

```
<PRE> #define INCL_DOSMISC
```

```
USHORT rc = DosPutMessage(FileHandle, MessageLength, MessageBuffer);
```

```
USHORT FileHandle; /* Handle of output file/device */ USHORT MessageLength; /* Length of message  
buffer */ PCHAR MessageBuffer; /* Message buffer */
```

```
USHORT rc; /* return code */ </PRE>
```

MASM Binding

```
<PRE> EXTRN DosPutMessage:FAR INCL_DOSMISC EQU 1
```

```
PUSH WORD FileHandle ;Handle of output file/device PUSH WORD MessageLength ;Length of message  
buffer PUSH@ OTHER MessageBuffer ;Message buffer CALL DosPutMessage
```

```
Returns WORD </PRE>
```

Note

Text based on [http://www.edm2.com/index.php/DosPutMessage_\(FAPI\)](http://www.edm2.com/index.php/DosPutMessage_(FAPI))

| Family API | | |
|------------|-----------------|--|
| DOS | Process Manager | DosBeep DosExit DosSleep DosExecPgm |
| | File Manager | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSInfo DosShutdown |
| | Memory Manager | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias |
| | NLS | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage |
| | Date and Time | DosSetDateTime DosGetDateTime |
| | Devices | DosDevConfig DosDevIOctI DosDevIOctI2 |
| | Signals | DosHoldSignal DosSetSigHandler |
| KBD | Misc | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec |
| | | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek |

| Family API | |
|-------------------|---|
| VIO | VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp |
| Tools | BIND |
| Modules | DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL |
| Libraries | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB |

2018/08/25 15:05 · prokushev · 0 Comments

From:
<https://osfree.su/doku/> - **osFree wiki**

Permanent link:
<https://osfree.su/doku/doku.php?id=en:docs:fapi:dosputmessage&rev=1629433071>

Last update: **2021/08/20 04:17**

