



This is part of **Win16 API** which allow to create versions of program from one source code to run under OS/2 and Win16. Under OS/2 program can be running under Win-OS/2 if program is Windows NE executable, and with help on Windows Libraries for OS/2, if it is OS/2 NE executable. [Here](#) is a WLO to OS/2 API mapping draft

2021/09/01 04:23 · prokushev · [0 Comments](#)

PostQuitMessage

Brief

The **PostQuitMessage** function posts a message to Windows indicating that an application is requesting to terminate execution (quit). This function is typically used in response to a `WM_DESTROY` message.

Syntax

```
VOID WINAPI PostQuitMessage(int nExitCode);
```

Parameters

- **nExitCode** — Specifies an application-defined exit code. It must be the **wParam** parameter of the `WM_QUIT` message.

Return Code

This function does not return a value.

Notes

- The `PostQuitMessage` function posts a `WM_QUIT` message to the application and returns immediately; the function simply indicates to the system that the application will request to quit some time in the future.
- When the application receives the `WM_QUIT` message, it should exit the message loop in the main function and return control to Windows.

Example Code

C Binding

```
#include <windows.h>

LRESULT CALLBACK __export WndProc(HWND hwnd, UINT msg, WPARAM wParam, LPARAM lParam)
{
    switch (msg)
    {
        case WM_DESTROY:
            PostQuitMessage(0);
            return 0;
    }
    return DefWindowProc(hwnd, msg, wParam, lParam);
}

int WINAPI WinMain(HANDLE hInstance, HANDLE hPrevInstance,
                  LPSTR lpCmdLine, int nCmdShow)
{
    MSG msg;

    /* ... window class registration and creation ... */

    while (GetMessage(&msg, NULL, 0, 0))
    {
        TranslateMessage(&msg);
        DispatchMessage(&msg);
    }

    return (int)msg.wParam;
}
```

MASM Binding

```
EXTRN PostQuitMessage:FAR

WndProc PROC FAR
    cmp     ax, WM_DESTROY
    je      handle_destroy
    ; ... other messages ...

handle_destroy:
    push    0                      ; nExitCode = 0
    call    PostQuitMessage
    xor     ax, ax                  ; return 0 (message handled)
    retf
WndProc ENDP
```

```
; Message loop that catches WM_QUIT
WinMain PROC FAR
    ; ... initialization ...

message_loop:
    lea     ax, msg
    push    ax                ; lpMsg
    push    0                ; hWnd
    push    0                ; wParamFilterMin
    push    0                ; wParamFilterMax
    call    GetMessage
    cmp     ax, 0
    je      exit_app         ; FALSE - WM_QUIT received

    lea     ax, msg
    push    ax
    call    TranslateMessage
    lea     ax, msg
    push    ax
    call    DispatchMessage
    jmp     message_loop

exit_app:
    mov     ax, msg.wParam    ; return exit code from WM_QUIT
    retf
WinMain ENDP
```

See also

- [MessageBox](#)
- [InitApp](#)
- [GetMessage](#)

Group	Functions
Module Management	GetVersion GetModuleHandle GetModuleUsage GetModuleFileName GetProcAddress MakeProcInstance FreeProcInstance GetInstanceData Catch Throw GetCodeHandle LoadLibrary FreeLibrary
Global Memory Management	GlobalAlloc GlobalCompact GlobalDiscard GlobalFree GlobalLock GlobalReAlloc GlobalSize GlobalUnlock GlobalFlags
Local Memory Management	LocalInit LocalAlloc LocalCompact LocalDiscard LocalFree LocalLock LocalFreeze LocalMelt LocalReAlloc LocalSize LocalUnlock LocalHandleDelta LockData UnlockData LocalFlags
Task Scheduling	GetCurrentTask Yield SetPriority
Resource Management	AddFontResource RemoveFontResource LoadBitmap LoadCursor LoadIcon LoadMenu LoadString LoadAccelerators FindResource LoadResource AllocResource LockResource FreeResource AccessResource SizeofResource SetResourceHandler
String Manipulation	AnsiUpper AnsiLower AnsiNext AnsiPrev AnsiUpperBuff AnsiLowerBuff Istrcmp Istrcmpi IsCharAlpha IsCharAlphaNumeric IsCharUpper IsCharLower _wsprintf wvsprintf

Group	Functions
Atom Management	InitAtomTable AddAtom DeleteAtom FindAtom GetAtomName GlobalAddAtom GlobalDeleteAtom GlobalFindAtom GlobalGetAtomName
Initialization Files	GetProfileInt GetProfileString WriteProfileString
Debugging	FatalExit
File Input/Output	_lopen _lcreat _lseek _lread _lwrite _lclose OpenFile GetTempFileName GetTempDrive
Registry	RegOpenKey RegCreateKey RegCloseKey RegDeleteKey RegSetValue RegQueryValue RegEnumKey
Window Management	CreateWindow CreateWindowEx DestroyWindow ShowWindow CloseWindow OpenIcon MoveWindow SetWindowPos BringWindowToTop GetWindow GetParent SetParent GetNextWindow GetTopWindow GetWindowRect GetClientRect AdjustWindowRect AdjustWindowRectEx EnableWindow IsWindowEnabled IsWindowVisible IsIconic IsZoomed IsWindow IsChild FindWindow EnumWindows EnumChildWindows EnumTaskWindows GetDesktopWindow GetDesktopHwnd WindowFromPoint ChildWindowFromPoint GetWindowText SetWindowText GetWindowTextLength GetClassName GetWindowLong SetWindowLong GetWindowWord SetWindowWord GetWindowTask GetWindowPlacement SetWindowPlacement ArrangeIconicWindows CascadeChildWindows TileChildWindows ShowOwnedPopups AnyPopup GetLastActivePopup SetActiveWindow GetActiveWindow SetFocus GetFocus SetCapture GetCapture ReleaseCapture SetSysModalWindow GetSysModalWindow LockWindowUpdate RedrawWindow UpdateWindow InvalidateRect InvalidateRgn ValidateRect ValidateRgn GetUpdateRect GetUpdateRgn ExcludeUpdateRgn BeginDeferWindowPos DeferWindowPos EndDeferWindowPos FlashWindow
Message Handling	GetMessage PeekMessage PostMessage PostAppMessage SendMessage ReplyMessage InSendMessage WaitMessage TranslateMessage DispatchMessage GetMessagePos GetMessageTime GetMessageExtraInfo PostQuitMessage RegisterWindowMessage SetMessageQueue GetQueueStatus GetInputState QuerySendMessage
Painting and Drawing	BeginPaint EndPaint GetDC GetDCEX GetWindowDC ReleaseDC DrawText GrayString TabbedTextOut GetTabbedTextExtent FillRect InvertRect FrameRect DrawFocusRect DrawIcon ScrollDC ScrollWindow ScrollWindowEx FillWindow PaintRect GetControlBrush
Menus	CreateMenu CreatePopupMenu DestroyMenu GetMenu SetMenu GetSystemMenu GetSubMenu AppendMenu InsertMenu ModifyMenu DeleteMenu RemoveMenu ChangeMenu CheckMenuItem EnableMenuItem HiLiteMenuItem GetMenuState GetMenuString GetMenuItemCount GetMenuItemID DrawMenuBar TrackPopupMenu GetMenuCheckMarkDimensions SetMenuItemBitmaps IsMenu
Clipboard	OpenClipboard CloseClipboard EmptyClipboard GetClipboardOwner GetOpenClipboardWindow SetClipboardData GetClipboardData CountClipboardFormats EnumClipboardFormats RegisterClipboardFormat GetClipboardFormatName IsClipboardFormatAvailable GetPriorityClipboardFormat SetClipboardViewer GetClipboardViewer ChangeClipboardChain
Caret	CreateCaret DestroyCaret SetCaretPos GetCaretPos HideCaret ShowCaret SetCaretBlinkTime GetCaretBlinkTime

Group	Functions
Cursor and Icon	SetCursor GetCursor SetCursorPos GetCursorPos ShowCursor ClipCursor GetClipCursor LoadCursor LoadIcon CreateCursor CreateIcon CopyCursor CopyIcon DestroyCursor DestroyIcon CreateCursorIconIndirect
Scroll Bars	SetScrollPos GetScrollPos SetScrollRange GetScrollRange ShowScrollBar EnableScrollBar CalcChildScroll
Dialog Boxes	DialogBox DialogBoxIndirect DialogBoxParam DialogBoxIndirectParam CreateDialog CreateDialogIndirect CreateDialogParam CreateDialogIndirectParam EndDialog GetDlgItem SetDlgItemText GetDlgItemText SetDlgItemInt GetDlgItemInt CheckDlgButton IsDlgButtonChecked CheckRadioButton SendDlgItemMessage GetNextDlgGroupItem GetNextDlgTabItem GetDlgCtrlID IsDialogMessage MapDialogRect GetDialogBaseUnits DefDlgProc DlgDirList DlgDirListComboBox DlgDirSelect DlgDirSelectEx DlgDirSelectComboBox DlgDirSelectComboBoxEx
Device Context Management	GetDC GetDCEX GetWindowDC ReleaseDC SaveDC RestoreDC CreateDC CreateCompatibleDC DeleteDC ResetDC
Coordinates and Transformations	SetMapMode GetMapMode SetWindowOrg GetWindowOrg SetWindowExt GetWindowExt SetViewportOrg GetViewportOrg SetViewportExt GetViewportExt OffsetWindowOrg OffsetViewportOrg ScaleWindowExt ScaleViewportExt DPtoLP LPtoDP
Drawing Functions	SetPixel GetPixel MoveTo LineTo Polyline Polygon PolyPolygon Rectangle RoundRect Ellipse Arc Chord Pie FloodFill ExtFloodFill DrawFocusRect PatBlt BitBlt StretchBlt StretchDIBits SetDIBits GetDIBits SetDIBitsToDevice
Regions	CreateRectRgn CreateRectRgnIndirect CreateRoundRectRgn CreateEllipticRgn CreateEllipticRgnIndirect CreatePolygonRgn CreatePolyPolygonRgn CombineRgn EqualRgn OffsetRgn FillRgn FrameRgn InvertRgn PaintRgn SelectClipRgn ExcludeClipRect IntersectClipRect OffsetClipRgn GetClipBox GetRgnBox PtInRegion RectInRegion SetRectRgn
Bitmaps	CreateBitmap CreateBitmapIndirect CreateCompatibleBitmap CreateDiscardableBitmap CreateDIBitmap CreateDIBPatternBrush SetBitmapBits GetBitmapBits SetBitmapDimension GetBitmapDimension
Brushes and Pens	CreateSolidBrush CreateHatchBrush CreatePatternBrush CreateBrushIndirect CreatePen CreatePenIndirect SetBrushOrg GetBrushOrg SelectObject GetObject DeleteObject GetStockObject UnrealizeObject
Fonts and Text	CreateFont CreateFontIndirect CreateScalableFontResource AddFontResource RemoveFontResource EnumFonts EnumFontFamilies GetTextMetrics GetTextExtent GetTextFace GetCharWidth GetCharABCWidths GetOutlineTextMetrics GetGlyphOutline GetKerningPairs SetTextColor GetTextColor SetBkColor GetBkColor SetBkMode GetBkMode SetTextAlign GetTextAlign SetTextCharacterExtra GetTextCharacterExtra SetTextJustification TextOut ExtTextOut TabbedTextOut GetTabbedTextExtent
Metafiles	CreateMetaFile CloseMetaFile DeleteMetaFile CopyMetaFile GetMetaFile GetMetaFileBits SetMetaFileBits PlayMetaFile PlayMetaFileRecord EnumMetaFile IsValidMetaFile
Printing	StartDoc EndDoc StartPage EndPage SetAbortProc AbortDoc QueryAbort OpenJob CloseJob DeleteJob WriteSpool StartSpoolPage EndSpoolPage SpoolFile
Palettes	CreatePalette SelectPalette RealizePalette GetPaletteEntries SetPaletteEntries ResizePalette AnimatePalette UpdateColors GetNearestPaletteIndex GetNearestColor SetSystemPaletteUse GetSystemPaletteUse GetSystemPaletteEntries
Device Capabilities	GetDeviceCaps GetRasterizerCaps GetEnvironment SetEnvironment GetAspectRatioFilter Escape CreateIC

Group	Functions
Miscellaneous GDI	SetROP2 GetROP2 SetPolyFillMode GetPolyFillMode SetStretchBltMode GetStretchBltMode SetMapperFlags GetMapperFlags LineDDA MulDiv GetCurrentPosition GetBoundsRect SetBoundsRect FastWindowFrame
Timer	SetTimer KillTimer GetTickCount GetTimerResolution GetCurrentTime
Hooks	SetWindowsHook SetWindowsHookEx UnhookWindowsHook UnhookWindowsHookEx CallNextHookEx DefHookProc CallMsgFilter
Communications	OpenComm CloseComm ReadComm WriteComm SetCommState GetCommState GetCommError TransmitCommChar SetCommEventMask GetCommEventMask SetCommBreak ClearCommBreak UngetCommChar BuildCommDCB EscapeCommFunction FlushComm EnableCommNotification
Networking (WNet)	WNetErrorText WNetOpenJob WNetCloseJob WNetAbortJob WNetHoldJob WNetReleaseJob WNetCancelJob WNetSetJobCopies WNetWatchQueue WNetUnwatchQueue WNetLockQueueData WNetUnlockQueueData WNetGetConnection WNetGetCaps WNetDeviceMode WNetBrowseDialog WNetGetUser WNetAddConnection WNetCancelConnection WNetGetError WNetGetErrorText WNetEnable WNetDisable WNetRestoreConnection WNetWriteJob WNetConnectDialog WNetDisconnectDialog WNetConnectionDialog WNetViewQueueDialog WNetPropertyDialog WNetGetDirectoryType WNetDirectoryNotify WNetGetPropertyText
System Information	GetSystemMetrics GetSysColor SetSysColors SystemParametersInfo GetFreeSystemResources GetSystemDebugState GetDoubleClickTime SetDoubleClickTime SwapMouseButton GetKeyState GetAsyncKeyState GetKeyboardState SetKeyboardState mouse_event GetMouseEventProc EnableHardwareInput IsUserIdle LockInput MessageBeep WinHelp
Window Classes	RegisterClass RegisterClassEx UnregisterClass GetClassInfo GetClassInfoEx GetClassWord SetClassWord GetClassLong SetClassLong GetClassName
Window Properties	SetProp GetProp RemoveProp EnumProps
MDI Support	DefFrameProc DefMDIChildProc TranslateMDISysAccel
Drivers	OpenDriver CloseDriver SendDriverMessage GetDriverModuleHandle GetDriverInfo GetNextDriver DefDriverProc
Miscellaneous	InitApp ExitWindows ExitWindowsExec OLDEXITWINDOWS BEAR11 BEAR86 BEAR182 UserSeeUserDo OldSetDeskPattern SetRect SetRectEmpty CopyRect IsRectEmpty PtInRect OffsetRect InflateRect IntersectRect UnionRect EqualRect SubtractRect

2022/11/17 15:22 · prokushev · 0 Comments

From:
<https://ftp.osfree.org/doku/> - osFree wiki

Permanent link:
<https://ftp.osfree.org/doku/doku.php?id=en:docs:win16:api:user:postquitmessage>

Last update: 2026/05/06 08:12

