2025/11/28 03:04 1/2 MouInitReal

MouInitReal

Bindings: C, MASM

This call initializes mouse pointer draw support for DOS mode.

MouInitReal (DriverName)

DriverName (**PSZ**) - input Address of the name of the Pointer Draw Device Driver used as the pointer-image drawing routine for the DOS mode session.

The name of the device driver must be included in the CONFIG.SYS file at system start-up time.

If the selector portion of the far address is zero and the offset portion is non-zero, the offset portion identifies the power-up display configuration.

rc (**USHORT**) - return Return code descriptions are:

	0	NO_ERROR
	385	ERROR_MOUSE_NO_DEVICE
	466	ERROR_MOU_DETACHED
	412	ERROR_MOUSE_SMG_ONLY
	501	ERROR_MOUSE_NO_CONSOLE
	505	ERROR_MOU_EXTENDED_SG

Remarks

MoulnitReal is issued by the Base Video Subsystem at system initialization time.

The DOS mode mouse API (INT 33H), in contrast to the OS/2 mode Mouse API, does not contain an OPEN command. In addition, there is only one session for DOS mode.

The default pointer draw routine for DOS mode is located in the same pointer draw device driver, POINTER\$, that is used for OS/2 mode. Establishing addressability to the pointer draw routine must be done during system initialization. This requires passing the entry point of the DOS mode pointer draw routine to the mouse device driver. This is the purpose of the MoulnitReal call. It passes the address of the default, power-up pointer draw routine for DOS mode to the mouse device driver. This initialization is transparent to applications.

This call is for use only by the Base Video Subsystem when invoked during system initialization under the shell/session manager PID.

The error code ERROR MOUSE SMG ONLY is valid from shell process only.

From:

http://osfree.su/doku/ - osFree wiki

Permanent link:

http://osfree.su/doku/doku.php?id=en:ibm:prcp:mou:initreal&rev=1454563463

Last update: 2016/02/04 05:24



http://osfree.su/doku/ Printed on 2025/11/28 03:04