



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

This call reads a string of characters from the display starting at the specified location.

Syntax

VioReadCharStr (CharStr, Length, Row, Column, VioHandle)

Parameters

;CharStr (PCH) - output : Address of the buffer where the character string is returned. ;Length (USHORT) - input/output : Address of the buffer length in bytes. ;Row (USHORT) - input : Starting row of the field to read, 0 is the top row. ;Column (USHORT) - input : Starting column of the field to read, 0 is the leftmost column. ;VioHandle (HVIO) - input : This must be zero unless the caller is a Presentation Manager application, in which case it must be the value returned by VioGetPs.

Return Code

rc (USHORT) - return Return code descriptions are: * 0 NO_ERROR * 355 ERROR_VIO_MODE * 358 ERROR_VIO_ROW * 359 ERROR_VIO_COL * 436 ERROR_VIO_INVALID_HANDLE * 465 ERROR_VIO_DETACHED

Remarks

If a string read comes to the end of the line and is not complete, then the string read continues at the beginning of the next line. If the read comes to the end of the screen and is not complete, the read terminates and the length is set to the number of characters read.

PM Considerations

VioReadCharStr reads a character string from the Advanced VIO presentation space starting at the specified location.

Example Code

C Binding

```
<PRE> #define INCL_VIO
```

```
USHORT rc = VioReadCharStr(CharStr, Length, Row, Column, VioHandle);
```

```
PCH CharStr; /* Character buffer */ PUSHORT Length; /* Length of buffer */ USHORT Row; /* Starting row location */ USHORT Column; /* Starting column location */ HVIO VioHandle; /* Video handle */
```

```
USHORT rc; /* return code */ </PRE>
```

MASM Binding

```
<PRE> EXTRN VioReadCharStr:FAR INCL_VIO EQU 1
```

```
PUSH@ OTHER CharStr ;Character buffer PUSH@ WORD Length ;Length of buffer PUSH WORD Row ;Starting row location PUSH WORD Column ;Starting column location PUSH WORD VioHandle ;Video handle CALL VioReadCharStr
```

```
Returns WORD </PRE>
```

Note

Text based on [http://www.edm2.com/index.php/VioReadCharStr_\(FAPI\)](http://www.edm2.com/index.php/VioReadCharStr_(FAPI))

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
KBD	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek

Family API	
VIO	VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools	BIND
Modules	DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
<https://osfree.su/doku/> - **osFree wiki**

Permanent link:
<https://osfree.su/doku/doku.php?id=en:docs:fapi:vioreadcharstr&rev=1629446909>

Last update: **2021/08/20 08:08**

